

AutoCAD Electrical 2018 – Missing Text in Dialogs

Issue:

When using AutoCAD Electrical 2018, you are finding that various text in settings / properties dialogs are missing. An example of this is shown below:

When a title block update is performed, the drawings to be processed are not shown in the dialogue.

Right click over the current activated project > Title block update.



Select at least one tick box and then OK Project-wide

The dialogue which should show drawings in the upper section (highlighted) is blank

This is an example of what should be shown:







sales@cadline.co.uk





Reference: October 2017 Guide by Mark Lavers

Page 2 of 3

Select Dr	awings to Process					×
) Dra	wing	O Description
Ref	Subfolder SCHEMATICS SCHEMATICS SCHEMATICS SCHEMATICS OPTION B	Section	Sub-Section	Project Drawing List C:\Training\tp4\1234-E-02.dwg C:\Training\tp4\1234-E-03.dwg C:\Training\tp4\1234-E-04.dwg C:\Training\tp4\1234-E-05.dwg C:\Training\tp4\pic01.dwg		
C Do Al	🔶 Prossi	🋉 Res	: 🎓 0	by Section/Jsub	section	by Subfolder
Ref	Subfolder	Section	Sub-Section	Project Drawing List		
< Select from	m the top list, the bottom list.		ок с	ancel Help		Vew

This is what you are finding:

select Drawings to Process		×
	Drawing	Description
C Do Al	by Section/aub-section	by Subfolder
Ref Subfolder	Section Sub-Section Project Drawing List	
٤		,
elect from the top list. roert into the bottom list.	CIK Cancel Help	Vere











Solution:

The cause of this would appear to be due to some modification / security policy of the user profiles that have been setup and points to the local temporary folder for the user. The solution is to change the local temp location.

- Create a new folder "Temp", located outside of the current users temp folder:
 i.e. C:\Temp
- Set the users environment variables to point to this new location:

Valiable	Value
OneDrive	C:\Users\MDL\OneDrive
Path	%USERPROFILE%\AppData\Local\Microsoft\WindowsApps;
TEMP	%USERPROFILE%\AppData\Local\Temp
тмр	%USERPROFILE%\AppData\Local\Temp
stem variables	New Edit Delete
stem variables Variable	Value
stem variables Variable CLASSPATH	Value C:\Program Files (x86)\SAP\SAP Business One DI API\JCO\LIB\sbow
stem variables Variable CLASSPATH ComSpec	Value C:\Program Files (x86)\SAP\SAP Business One DI API\JCO\LIB\sbow C:\WINDOWS\system32\cmd.exe
stem variables Variable CLASSPATH ComSpec IPOFFICEADMIN_DIR	Value C:\Program Files (x86)\SAP\SAP Business One DI API\JCO\LIB\sbow C:\WINDOWS\system32\cmd.exe C:\Program Files (x86)\Avaya\IP Office\
stem variables Variable CLASSPATH ComSpec IPOFFICEADMIN_DIR IPOFFICEADMIN_VER	Value C:\Program Files (x86)\SAP\SAP Business One DI API\JCO\LIB\sbow C:\WINDOWS\system32\cmd.exe C:\Program Files (x86)\Avaya\IP Office\ 10.0.100.53
stem variables Variable CLASSPATH ComSpec IPOFFICEADMIN_DIR IPOFFICEADMIN_VER NUMBER_OF_PROCESSORS	Value C:\Program Files (x86)\SAP\SAP Business One DI API\JCO\LIB\sbow C:\WINDOWS\system32\cmd.exe C:\Program Files (x86)\Avaya\IP Office\ 10.0.100.53 2
stem variables Variable CLASSPATH ComSpec IPOFFICEADMIN_DIR IPOFFICEADMIN_VER NUMBER_OF_PROCESSORS OS	Value C:\Program Files (x86)\SAP\SAP Business One DI API\JCO\LIB\sbow C:\WINDOWS\system32\cmd.exe C:\Program Files (x86)\Avaya\IP Office\ 10.0.100.53 2 Windows_NT
stem variables Variable CLASSPATH ComSpec IPOFFICEADMIN_DIR IPOFFICEADMIN_VER NUMBER_OF_PROCESSORS OS Path	Value C:\Program Files (x86)\SAP\SAP Business One DI API\JCO\LIB\sbow C:\WINDOWS\system32\cmd.exe C:\Program Files (x86)\Avaya\IP Office\ 10.0.100.53 2 Windows_NT C:\Program Files (x86)\Parallels\Parallels Tools\Applications:C:\Pro





cadlíne